SUM AUTOMATION

Robot Framework

Libraries Used:

Installations Required

Python 3.8.2 (Latest Version):

Selenium:

Robot Framework:

Robot Framework Libraries:

Python Libraries:

SSH setup on Windows: (Required by target node):

Visual Studio Code: (Optional)

Flow of Execution

Script to be run by user:

- 1. Required Parameters are provided:
- 2. No parameters are provided:

Ping and SSH on to the server:

Removal of logs:

Launching of SUM_Station:

Gathering Logs:

SUM AUTOMATION

Robot Framework

Robot Framework is a generic open source automation framework for acceptance testing, acceptance test driven development (ATDD), and robotic process automation (RPA). It has easy-to-use tabular test data syntax and it utilizes the keyword-driven testing approach. Its testing capabilities can be extended by test libraries implemented either with Python or Java, and users can create new higher-level keywords from existing ones using the same syntax that is used for creating test cases.

Libraries Used:

1. Built-in:

This is the default library that need not be included at the beginning of the Robot code. https://robotframework.org/robotframework/latest/libraries/BuiltIn.html

2. Operating System:

This library is required to access the file systems and command propmt if required. https://robotframework.org/robotframework/latest/libraries/OperatingSystem.html

3. Collections:

This library is required to create List and Dictionaries. It also has all the oprations that has to be done on Lists and Dictionaries.

https://robotframework.org/robotframework/latest/libraries/Collections.html

4. String:

This library includes strings and its operations. Conversions, Splitting, Reversing etc. https://robotframework.org/robotframework/latest/libraries/Collections.html

5. Process:

This library is used to start any windows process even the terminal. It is also used to termnate certain processes. For example in order to terminate the web browser this library is used.

https://robotframework.org/robotframework/latest/libraries/Process.html

6. Selenium2Library:

This library is used simulate the user actions on the web browser. With the help of web driver, it controls the actions of the web-browser.

https://robotframework.org/Selenium2Library/Selenium2Library.html

Installations Required

Python 3.8.2 (Latest Version):

- Go to https://www.python.org/downloads/ and download latest version of python for windows/linux.
- Go to the directory where python has been installed. Copy the path to python.exe and scripts. Add it to the system variables.
- Open command prompt and type "py" to verify the proper installation of python.
- Install PIP from any git repository.
- Note: Remove previous versions of python before the installation.

Selenium:

Open command prompt and type "pip install -U selenium"

```
C:\Users\ssumanth>pip install -U selenium

Collecting selenium

Using cached selenium-3.141.0-py2.py3-none-any.whl (904 kB)

Requirement already satisfied, skipping upgrade: urllib3 in c:\users\ssumanth\appdata\local\programs\python\python38-32

lib\site-packages (from selenium) (1.25.8)

Installing collected packages: selenium

Successfully installed selenium-3.141.0
```

Enter into the python environment(just enter py or python) and enter "from selenium" import webdriver". No error should indicate the proper installation.

```
C:\Users\ssumanth>py
Python 3.8.1 (tags/v3.8.1:1b293b6, Dec 18 2019, 22:39:24) [MSC v.1916 32 bit (Intel)] on win32
Type "help", "copyright", "credits" or "license" for more information.
>>> from selenium import webdriver
```

• Download selenium web-driver (particular web browser has particular web-drivers). Download that version of web-driver which supports the web browser you have. (For Firefox it is geckodriver.exe) https://github.com/mozilla/geckodriver/releases .

geckodriver-v0.26.0-linux32.tar.gz	2.22 MB
geckodriver-v0.26.0-linux64.tar.gz	2.28 MB
geckodriver-v0.26.0-macos.tar.gz	1.91 MB
geckodriver-v0.26.0-win32.zip	1.37 MB
geckodriver-v0.26.0-win64.zip	1.46 MB
Source code (zip)	
Source code (tar.gz)	

• Copy the geckodriver.exe file to the python *scripts* folder.

DLLs	1/14/2020 10:09 AM	File folder	
Doc	1/14/2020 10:08 AM	File folder	
- ExcelRobotTest	3/17/2020 8:29 PM	File folder	
include	1/14/2020 10:08 AM	File folder	
Lib	1/14/2020 10:08 AM	File folder	
libs	1/14/2020 10:08 AM	File folder	
Scripts	3/17/2020 8:54 PM	File folder	
tcl tcl	1/14/2020 10:09 AM	File folder	
Tools	1/14/2020 10:08 AM	File folder	
LICENSE.txt	12/18/2019 11:26	Text Document	31 KB
NEWS.txt	12/18/2019 11:27	Text Document	859 KB
python.exe	12/18/2019 11:26	Application	96 KB
python3.dll	12/18/2019 11:26	Application extens	58 KB
python38.dll	12/18/2019 11:26	Application extens	3,834 KB
🥫 pythonw.exe	12/18/2019 11:26	Application	94 KB
vcruntime140.dll	12/18/2019 11:27	Application extens	85 KB

Robot Framework:

• Open command prompt and enter "pip install robotframework"

```
C:\Users\ssumanth>pip install robotframework
Collecting robotframework
Using cached robotframework-3.1.2-py2.py3-none-any.whl (602 kB)
Installing collected packages: robotframework
Successfully installed robotframework-3.1.2
```

 verifying the installation cmd>> pip show robotframework cmd>> pip check

```
C:\Users\ssumanth>pip show robotframework
Name: robotframework
Version: 3.1.2
Summary: Generic automation framework for acceptance testing and robotic process automation (RPA)
Home-page: http://robotframework.org
Author: Pekka Klärck
Author-email: peke@eliga.fi
License: Apache License 2.0
Location: c:\users\ssumanth\appdata\local\programs\python\python38-32\lib\site-packages
Requires:
Required-by: robotframework-seleniumlibrary, robotframework-excellib, robotframework-excel,
robotframework-datadriver
```

• Add ".\python38-32**\Lib\site-packages**" to the system variables. This is the folder where all the libraries of robot framework would be present.

Robot Framework Libraries:

pip install selenium2library

```
C:\Users\ssumanth>pip install robotframework-selenium2library
Collecting robotframework-selenium2library
Using cached robotframework_selenium2library-3.0.0-py2.py3-none-any.whl (6.2 kB)
Requirement already satisfied: robotframework-seleniumlibrary>=3.0.0 in c:\users\ssumanth\appdata\local\programs\python\python38-32\lib\site-packages (from robotframework-selenium2library) (4.2.0)
Requirement already satisfied: robotframework>=3.0.4 in c:\users\ssumanth\appdata\local\programs\python\python38-32\lib\site-packages (from robotframework-selenium1ibrary>=3.0.0->robotframework-selenium2library) (3.1.2)
Requirement already satisfied: selenium>=3.141.0 in c:\users\ssumanth\appdata\local\program s\python\python38-32\lib\site-packages (from robotframework-selenium1ibrary>=3.0.0->robotframework-selenium2library) (3.141.0)
Requirement already satisfied: urllib3 in c:\users\ssumanth\appdata\local\programs\python\python38-32\lib\site-packages (from selenium>=3.141.0->robotframework-selenium1ibrary>=3.0.0->robotframework-selenium2library) (1.25.8)
Installing collected packages: robotframework-selenium2library
Successfully installed robotframework-selenium2library-3.0.0
```

• No need to install other libraries as it will be automatically installed with robot framework.

Python Libraries:

pip install paramiko

```
C:\Users\ssumanth>pip install paramiko
Collecting paramiko
  Downloading paramiko-2.7.1-py2.py3-none-any.whl (206 kB)
                                              | 206 kB 328 kB/s
Collecting cryptography>=2.5

Downloading cryptography-2.8-cp38-cp38-win32.whl (1.3 MB)
                                             | 1.3 MB 501 kB/s
Collecting bcrypt>=3.1.3
 Downloading bcrypt-3.1.7-cp38-cp38-win32.whl (26 kB)
Collecting pynacl>=1.0.1
  Downloading PyNaCl-1.3.0-cp38-cp38-win32.whl (179 kB)
                                             | 179 kB 384 kB/s
Requirement already satisfied: six>=1.4.1 in c:\users\ssumanth\appdata\local\programs\pytho
n\python38-32\lib\site-packages (from cryptography>=2.5->paramiko) (1.11.0)
Collecting cffi!=1.11.3,>=1.8

Downloading cffi-1.14.0-cp38-cp38-win32.whl (165 kB)
                                             | 165 kB 312 kB/s
Collecting pycparser
Downloading pycparser-2.20-py2.py3-none-any.whl (112 kB)
                                             112 kB 409 kB/s
Installing collected packages: pycparser, cffi, cryptography, bcrypt, pynacl, paramiko
Successfully installed bcrypt-3.1.7 cffi-1.14.0 cryptography-2.8 paramiko-2.7.1 pycparser-
.20 pynacl-1.3.0
```

SSH setup on Windows: (Required by target node):

- complete setup guide is provided in this link https://winscp.net/eng/docs/guide windows op enssh server .
- Download the latest OpenSSH for Windows binaries (package OpenSSH-Win64.zip or OpenSSH-Win32.zip)
- As the Administrator, extract the package to C:\Program Files\OpenSSH
- As the Administrator, install sshd and ssh-agent services with the command: powershell.exe
 -ExecutionPolicy Bypass -File install-sshd.ps1 (must be present in the directory where
 openSSH is extracted).
- Either run the following PowerShell command (Windows 8 and 2012 or newer only), as the Administrator: New-NetFirewallRule -Name sshd -DisplayName 'OpenSSH SSH Server' -Enabled True -Direction Inbound -Protocol TCP -Action Allow -LocalPort 22
- Or go to Control Panel > System and Security > Windows Firewall1 > Advanced Settings > Inbound Rules and add a new rule for port 22.
- Go to Control Panel > System and Security > Administrative Tools and open Services. Locate OpenSSH SSH Server service.
- If you want the server to start automatically when your machine is started: Go to Action >
 Properties. In the Properties dialog, change Startup type to Automatic and confirm.
- Start the OpenSSH SSH Server service by clicking the Start the service.

Visual Studio Code: (Optional)

- Download VS code from this link and install it https://code.visualstudio.com/download .
- Add extension "Robot Framework Intellisense"
- Make sure that all the files that are created must be in same directory

Flow of Execution

Script to be run by user:

• Sum_Automation.py py file that need to run along with a parameter to skip the user interface.

```
Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\Users\Administrator\Documents\Robot\Test_cases>py Sum_automation.py --input c:\Users\Administrator\Desktop\input.txt
```

1. Required Parameters are provided:

1. For performing only prerequisites:

```
py Sum_automation.py --prerequisite_only --input
<input_file_dir/input_file_name.txt>
```

Prerequisites involves:

- Clearing iLO repository.
- Uninstallation of OFED from Linux machine.
- Rebooting the machine.
- 2. For running the entire script along with prerequisites:

```
py Sum_automation.py --prerequisite --input
<input_file_dir/input_file_name.txt>
```

3. For execution of the automation script only:

```
py Sum_automation.py --input <input_file_dir/input_file_name.txt>*
```

Input File Format:

- User has to edit an input file before running the script in this mode.
- If there is no new entry to the text file, then the script will continue with the old data.
- If there is no data given in the input file, then the script would terminate immediately.
- The required template is provided within the text file itself and user must strictly follow the template.

```
input.txt - Notepad

File Edit Format View Help

#INPUT FILE

SPP_DIR= D:\spp

SPP_ISO= SPP2020090.2020_0622.97.iso

CUSTOM_BASELINE_DIR= None

CO_DRIVE= E:

OUTPUT_PATH= D:

#SERVER DETAILS

#ilO/Network IP> <username> <password> <Linux/Windows/iLO-ESXi> <Firmware/Driver/Both/All/FW_All>
192.168.2.105 Administrator Hptc_ib Windows Both
192.168.2.104 root Hptc_ib Linux Both
192.168.5.123 admin admin123 iLO-ESXi Both
```

- SPP_ISO= requires spp name as the input.
- SPP_DIR= requires the directory where the spp is stored.
- CD_DRIVE= requires name of the drive where spp will mount.
- CUSTOM_BASELINE_DIR= path where the custom baseline is stored. If there are no custom baseline then mention None

• OUTPUT_PATH= path where the logs are colleted.

Note:(Enter the details as thown in the example with no extra backward slashes.

• User can comment line with "#". Commented server will not be considered.

```
input.bt - Notepad

File Edit Format View Help

#INPUT FILE

SPP_DIR= D:\spp

SPP_ISO= SPP2020090.2020_0622.97.iso

CUSTOM_BASELINE_DIR= None

CD_DRIVE= E:

OUTPUT_PATH= D:


#SERVER DETAILS


#<iLO/Network IP> <username> <password> <Linux/Windows/iLO-ESXi> <Firmware/Driver/Both/All/FW_All>
192.168.2.105 Administrator Hptc_ib Windows Both
192.168.2.104 root Hotc ib Linux Both

#192.168.5.123 admin admin123 iLO-ESXi Both
```

2. No parameters are provided:

User interface will pop-up.





- User has to fill all the required fields.
- Selection of spp.iso, output path and giving the cd-drive name is must. (provide only cd drive name without colon and backward slash. Ex: CD Drive Name = E)
- Also minimum of one server details must be provided before submitting.
- If user doesn't want to enter any details then he can close the interface. Script would continue with the previously present data of the input file.

Ping and SSH on to the server:

- All the servers would be pinged and checked for the reachability.
- If the server is reachable then ssh is done with the credentials provided.
- If both the criteria is cleared then only that particular server would be considered as a valid node. The failed ones would be discarded.

Removal of logs:

- Logs from the Localhost is removed even before launching the sum station.
- Logs from the remote node is removed during the ssh test.

Launching of SUM_Station:

- Firefox browser must be made as a default web browser.
- launch_sum.bat will be launched.
- If there is any problem with loading a web page or internet connection, script automatically re-launches the launch sum.bat file.
- Baseline addition will be checked. If not added script would add it.
- If custom baseline is provided then it will also be added.
- First node in the list would be added.
- Inventory -> Components are selected -> Deploy

Selection of components:

- User should mention whether firmware/driver/Both/All components that needs to be deployed.
- User should also edit Text_files/search.txt file.

```
File Edit Format View Help

HPE Mellanox MFT Driver
HPE Mellanox RoCE
firmware-nic-mellanox
firmware-hca-mellanox
Online Firmware Upgrade Utility (Windows x64)
Online Firmware Upgrade Utility (ESXi 6.5
Online Firmware Upgrade Utility (ESXi 6.7
```

This text file consists of necessary keywords required for the selection of required components. These keywords would be searched for a match against the list of components during the deployment

 If the user does not want any particular key word not to be searched fro in the components list, then he can comment that line by inserting "# followed by a space"

```
File Edit Format View Help

# HPE Mellanox MFT Driver
# HPE Mellanox RoCE
firmware-nic-mellanox
firmware-hca-mellanox
Online Firmware Upgrade Utility (Windows x64)
Online Firmware Upgrade Utility (ESXi 6.5
Online Firmware Upgrade Utility (ESXi 6.7
```


Gathering Logs:

- Once the deployment is finished successfully, output logs of each component is collected.
- The logs are store in
 OUTPUT_PATH\spp_name\output_logs\ip_address\component_name.txt

- Overall result of the node will be stored in
 OUTPUT_PATH\spp_name\output_logs\ip_address\result.txt
- After the execution of entire process, **Dashboard** would appear containing details of every node and its result.

Dashboard					
IP_Address	Component	Status			
192.168.2.133	-	Failed_to_login_to_the_system(SSH_Failed)			
192.168.2.125	FIRMWARE-NIC-MELLANOX-IB-CX4-CX5-1.0.5-1.1.X86_64	Success.	View		
192.168.2.125	FIRMWARE-NIC-MELLANOX-ETHERNET-ONLY-1.0.12-1.1.X86_64	Success.	View		
192.168.2.125	FIRMWARE-HCA-MELLANOX-VPI-CONNECTX4-1.0.8-1.1.X86_64	Success.	View		
192.168.2.131	MLNX-OFA_KERNEL-4.7-OFED.4.7.3.2.9.1.G457F064.SLES15SP1.X86_64	Update returned error	View		
192.168.2.131	MLNX-OFA_KERNEL-KMP-DEFAULT-4.7_K4.12.14_195-OFED.4.7.3.2.9.1.G457F064.SLES15SP1.X86_64	Update returned error	View		
192.168.2.131	KERNEL-MFT-MLNX-KMP-DEFAULT-4.13.0_K4.12.14_195-1.SLES15SP1.X86_64	Success.	View		
192.168.2.131	MFT-4.13.0-102.SLES15SP1.X86_64	Success.	View		

• User can directly view the log of each component from the dashboard.



Zip file SUM_SUT_Logs.zip is also collected in
 OUTPUT_PATH\spp_name\output_logs\ip_address\

gather_logs	3/12/2020 1:09 AM	File folder	
error.txt	3/12/2020 12:44 AM	Text Document	0 KB
FIRMWARE-HCA-MELLANOX-VPI-CON	3/12/2020 1:09 AM	Text Document	2 KB
FIRMWARE-NIC-MELLANOX-ETHERNET	3/12/2020 1:09 AM	Text Document	2 KB
FIRMWARE-NIC-MELLANOX-IB-CX4-CX	3/12/2020 1:09 AM	Text Document	2 KB
result.txt	3/12/2020 1:09 AM	Text Document	1 KB
SUM_SUT_Logs_03-12-2020_01-09-29.zip	3/12/2020 1:09 AM	Compressed (zipp	9,317 KB